

```
#== BEGIN Menu Entries =====#
```

```
# Ubuntu / Kubuntu
```

```
menuentry "foxclone53" --class fox --class linux {
    set root='(hd0,1)'
    set isofile="/iso/foxclone53-bionic.iso"
    loopback loop $isofile
    linux (loop)/casper/vmlinuz boot=casper iso-scan/filename=${isofile} fsck.mode=skip quiet splash
    initrd (loop)/casper/initrd.lz
}
```

```
# IFL
```

```
menuentry "Image for Linux" --class ifl --class linux {
    set root='(hd0,1)'
    set isofile="/iso/IFL356.ISO"
    cfgfile="/boot/grub/grub.cfg"
    export isofile
    loopback loop (hd0,1)$isofile
    root=(loop)
    configfile $cfgfile
    loopback --delete loop
}
```

```
# Ubuntu
```

```
menuentry "Rescuezilla Deutsch" --class rescuezilla --class linux {
    set root='(hd0,1)'
    set isofile="/iso/rescuezilla-2.5.1-64bit.noble.iso"
    loopback loop $isofile
    linux (loop)/casper/vmlinuz boot=casper iso-scan/filename=${isofile} locale=de_DE console-setup/layoutcode=de console-setup/
    variantcode=nodeadkeys bootkbd=de fsck.mode=skip quiet splash
    initrd (loop)/casper/initrd.lz
}
```

```
# Debian
```

```
menuentry "Dr.Parted" --class drparted --class linux {
    set root='(hd0,1)'
    set isofile="/iso/Dr.Parted-Live25.02-amd64.iso"
    loopback loop $isofile
    linux (loop)/live/vmlinuz-6.12.11-amd64 boot=live findiso=${isofile} components noeject
    initrd (loop)/live/initrd.img-6.12.11-amd64
}
```

```
# IFL
```

```
!menuentry "Image for Linux ohne Auswahl" --class ifl --class linux {
    set root='(hd0,1)'
    set isofile="/iso/IFL356.ISO"
    loopback loop (hd0,1)$isofile
    linux (loop)/vmlinuz vga=791 switchx=yes iflkmap=de-latin1-nodeadkeys ktl=qwertz initrd=initrmfs.gz iflbfalg=0
    initrd (loop)/initrmfs.gz
}
```

```
# Ubuntu
```

```
!menuentry "Rescuezilla English" --class rescuezilla --class linux {
    set root='(hd0,1)'
    set isofile="/iso/rescuezilla-2.5.1-64bit.noble.iso"
    loopback loop $isofile
    linux (loop)/casper/vmlinuz boot=casper iso-scan/filename=${isofile} fsck.mode=skip quiet splash
    initrd (loop)/casper/initrd.lz
}
```

```
# Ubuntu
```

```
!menuentry "Rescuezilla" --class rescuezilla --class linux {
```

```
set root='(hd0,1)'
set isofile="/iso/rescuezilla-2.5.1-64bit.noble.iso"
loopback loop $isofile
linux (loop)/casper/vmlinuz boot=casper iso-scan/filename=${isofile} quiet splash vt.global_cursor_default=0 loglevel=2
rd.systemd.show_status=false rd.udev.log-priority=3 sysrq_always_enabled=1 cow_spacesize=1G ${locale_opts}
initrd (loop)/casper/initrd.lz
}

# Ubuntu / Kubuntu
!menuentry "foxclone53 alt" --class ubuntu --class linux {
    set root='(hd0,1)'
    set isofile="/iso/foxclone53-bionic.iso"
    loopback loop $isofile
    linux (loop)/casper/vmlinuz boot=casper iso-scan/filename=${isofile} quiet splash vt.global_cursor_default=0 loglevel=2
    rd.systemd.show_status=false rd.udev.log-priority=3 sysrq_always_enabled=1 cow_spacesize=1G
    initrd (loop)/casper/initrd.lz
}

menuentry "supergrub2disk" --class sg2d --class linux {
    set root='(hd0,1)'
    set isofile="/iso/supergrub2-classic-2.06s4-multiarch-CD.iso"
    cfgfile="/boot/grub/grub.cfg"
    export isofile
    loopback loop (hd0,1)$isofile
    root=(loop)
    configfile $cfgfile
    loopback --delete loop
}
```